

6008805

```
santa-sb# conf t
```

Enter configuration commands, one per line.  
Edit with DELETE CTRL/W, CTRL/U; end with CTRL/Z

```
interface serial 1  
encapsulation ppp  
^Z
```

```
santa-sb# sh int s 1
```

Serial 1 administratively down, line protocol is down  
Hardware is MCI Serial  
MTU 1500 bytes, BW 1544 Kbit, DLY 20000 usec, rely 255/255, load 1/255  
Encapsulation PPP, loopback not set, keepalive set (10 sec)

Fig. 1  
(Prior art)

RECEIVED

OCT 1 1993




Fig. 2  
(Prior art)

RECEIVED  
JUN 14 1996  
FBI  
JUN 14 1996





Fig. 3  
(Prior art)

RECEIVED  
APR 1 1990



RECEIVED  
JUN 14 1999

Fig. 4

```

5.1 <filename>onf.dat
1) flportCntEntry 1.3.6.1.4.1.351.100.4.2.1.1.1 Aggregate not-accessible
704 {
5.2 <filename>defs

706 {
1) flportCntEntry flportCntTable.1 Aggregate not-accessible mandatory
2) %ei flportCntEntry "flportSlotIndex" flportPortIndex"
708 {
3) flportPortIndex flportCntEntry.1 INTEGER read-only mandatory
4) %er flportSlotIndex 1 32
710 {
5) flportPortIndex flportCntEntry.2 INTEGER read-only mandatory
6) %er flportPortIndex 1 32

712 {
7) flportClockType flportCntEntry.3 INTEGER read-write mandatory
8) %ev flportClockType normal 1
9) %ev flportClockType looped 2
10) %ev flportClockType none 3

714 {
11) flportOperStatus flportCntEntry.4 INTEGER read-only mandatory
12) %ev flportOperStatus inactive 1
13) %ev flportOperStatus active 2
14) %ev flportOperStatus looped 3
15) %ev flportOperStatus failed 4
716 {
16) flportPollVerTmr flportCntEntry.5 INTEGER read-write mandatory
17) %er flportPollVerTmr 5 30
718 {
18) %er flportDescrpt flportCntEntry.6 Octetstring read-write mandatory

```

RECEIVED  
OCT 14 1992

800

802 { FrameRelay Local Port Configure Slot 2 Port1

804 { Frame Relay Local Port Configure Slot:  
• 2

806 { Frame Relay Local Port Configure Slot:  
• 1

808 { Frame Relay Local Port Configure Clock Type:  
• [Normal]  
• Looped  
• None

810 { Frame Relay Local Port Configure Oper Status :  
• Inactive

812 { Frame Relay Local Port Configure Verification Timer :  
• 5  
• To change, enter new value in the range 5-30 and select Change  
• 51

814 { Frame Relay Local Port Configure Description :  
• IBM Mainframe Port  
• To change, enter new string and select change  
•

Fig. 6